

Q1053

A Quilter's Home

by Nancy's Cupboard

* Backing Only
** Bag Lining

WH: Wall Hanging
Approximate Size: 40" X 43"




A: 59000-247 (24" x 43")
WH: 1 Panel 2/3 yd



Suggested
Scrapbook
Covers



B: 59001-234
TB: 2/3 yd



C: 59002-357**
TB: 1 1/8 yds



D: 59003-247
WH: 1 1/8 yds



E: 59004-347
TB: 2/3 yd



F: 59005-222
WH: 5/8 yd



G: 59005-347
TB: 5/8 yd



H: 59006-333
WH: 2/3 yd



I: 59006-444*
WH: 2 3/4 yds



TB: Tote Bag
Approximate Size: 12" X 12" X 6"

FREE
PATTERN
OFFERED
IN INDEPENDENT
QUILT SHOPS TO
COMPLEMENT THIS
FABRIC COLLECTION

Complements



J: Q1013-51000-440
WH: 2/3 yd



L: Q1080-31588-757
WH: 2/3 yd



K: Q1013-51000-525
WH: 2/3 yd



A Quilter's Home

Please read all instructions carefully before starting. All instructions include a 1/4" seam allowance and strips are cut from selvage to selvage unless otherwise stated.

Wall Hanging Instructions

approximate size: 40" x 43"

1. Cut the following:

Fabric A - **cut 1 - 19 1/2" x 23 1/2"

Fabric D - cut 2 - 3 1/2" strips, subcut 16 - 3 1/2" squares

cut 4 - 3 7/8" strips, subcut 31 - 3 7/8" squares, cut in half diagonally for 62 triangles ☐

cut 2 - 4 1/4" x 4 1/4" squares, cut in half diagonally from both directions for 6 triangles ☒

Fabric F - Borders: cut 2 - 2" strips, subcut 2 - 2" x 24 1/2" (Sides)

cut 2 - 1 1/2" strips, subcut 2 - 1 1/2" x 23 1/2" (Top and Bottom)

cut 4 - 1 3/4" strips, subcut 2 - 1 3/4" x 40 1/2" (Sides) and 2 - 1 3/4" x 40" (Top and Bottom)

Fabric H - cut 2 - 3 7/8" strips, subcut 11 - 3 7/8" squares, cut in half diagonally for 22 triangles ☐

cut 1 - 4 1/4" x 4 1/4" square, cut in half diagonally from both directions for 1 triangle ☒

Borders - cut 3 - 1" strips, subcut ** 1 - 1" x 23 1/2", 1 - 1" x 24 1/2" and 1 - 1" x 39 1/2"

BINDING - cut 1 - 2 1/4" strip

Fabric J - cut 1 - 3 7/8" strip, subcut 6 - 3 7/8" squares, cut in half diagonally for 12 triangles ☐

cut 1 - 4 1/4" x 4 1/4" square, cut in half diagonally from both directions for 2 triangles ☒

Borders: cut 3 - 1" strips, subcut ** 1 - 1" x 20 1/2", 1 - 1" x 26 1/2" and 1 - 1" x 37 1/2"

BINDING - cut 2 - 2 1/4" strips, sew end to end

Fabric K - cut 2 - 3 7/8" strips, subcut 11 - 3 7/8" squares, cut in half diagonally for 22 triangles ☐

cut 1 - 4 1/4" x 4 1/4" square, cut in half diagonally from both directions for 1 triangle ☒

Borders: cut 3 - 1" strips, subcut ** 1 - 1" x 23 1/2", 1 - 1" x 24 1/2" and 1 - 1" x 39 1/2"

BINDING - cut 1 - 2 1/4" strip

Fabric L - cut 1 - 3 7/8" strip, subcut 6 - 3 7/8" squares, cut in half diagonally for 12 triangles ☐

cut 1 - 4 1/4" x 4 1/4" square, cut in half diagonally from both directions for 2 triangles ☒

Borders: cut 3 - 1" strips, subcut ** 1 - 1" x 20 1/2", 1 - 1" x 26 1/2" and 1 - 1" x 37 1/2"

BINDING - cut 2 - 2 1/4" strips, sew end to end


2. Piecing Order:

1. Sew **H** and **K** 1" x 23 1/2" borders to the SIDES of center panel **A** 19 1/2" x 23 1/2", then sew **L** and **J** 1" x 20 1/2" to the TOP and BOTTOM according to the diagram. ** (If A measurements are slightly different, cut borders slightly wider, sew around **A**, then trim center block to measure 20 1/2" x 24 1/2".)


2. Sew **F** 2" x 24 1/2" to the SIDES of the wall hanging, then sew **F** 1 1/2" x 23 1/2" to the TOP and BOTTOM.

3. Sew **L** and **J** 1" x 26 1/2" to the SIDES of the wall hanging, then sew **K** and **H** 1" x 24 1/2" to the TOP and BOTTOM according to the diagram.


* Center of wall hanging measures 24" x 27" finished (24 1/2" x 27 1/2" unf.)



4. Make the following half square triangle units by sewing $3\frac{7}{8}$ " triangles together according to the diagrams: Press units toward the darker fabrics.



5. Make quarter square triangle units by first sewing pairs of $4\frac{1}{4}$ " triangles together, press toward the darker fabric, then sew triangle pairs and $3\frac{7}{8}$ " triangles together according to the diagrams.




6. Sew individual borders together by rows of units according to the diagram of the quilt. Pay close attention to the direction of each unit per border. Sew **SIDE** borders to the quilt first, then sew **TOP** and **BOTTOM** borders.

7. Sew **H** and **K** $1"$ x $39\frac{1}{2}"$ to the **SIDES** of the quilt, then sew **L** and **J** $1"$ x $37\frac{1}{2}"$ to the **TOP** and **BOTTOM** according to the diagram.

8. Sew **F** $1\frac{3}{4}"$ borders around the quilt, **SIDES** first, then **TOP** and **BOTTOM** borders.

9. The Wall Hanging measures approximately $40"$ x $43"$. Make backing (**Fabric I**) at least $6"$ larger than the top. Layer and baste top, batting and backing together. Quilt as desired. Prepare binding by pressing strips in half. Binding strips may be sewn to each side separately with corners mitered or sew binding strips end to end, press in half then sew one long scrappy binding strip to the wall hanging. Enjoy!!



Tote Bag Instructions

approximate size 12" x 12" x 6"

1. Cut the following:

Fabric B - cut 2 - 8 1/2" x 18 1/2" border stripes for pockets

Fabric C - lining - cut 2 - 15 1/2" x 18 1/2"
pocket lining cut 2 - 8 1/2" x 18 1/2"

Fabric E - cut 2 - 15 1/2" x 18 1/2" (Front and Back)


Fabric G - Handles - cut 2 - 6" strips

BATTING - cut 2 - 15 1/2" x 18 1/2"

2. Piecing Order:


1. Handles: Double fold two 6" **G** strips. First, press both strips in half, then open strips and fold both edges to the center pressed line. Press. Next, fold again and match folded edges. Press. Topstitch 1/8" along both sides of each handle for 2 - 1 1/2" x 40" handles.

2. Pockets: Place pocket lining **C** 8 1/2" x 18 1/2" over **B**, right sides together. Match corners and pin to secure layers. Stitch top and bottom seams only on both pockets. Turn pockets right sides out and press.



3. Place **E** 15 1/2" x 18 1/2" over batting. Place bottom edge of pocket 3 1/2" from the bottom of **E** (both right sides up).

Use walking foot and attach pocket to **E** by stitching along bottom edge of pocket. Make 2.




4. Next, move pocket out of the way and pin handles in place at least 5" below the top of **E** according to the diagram.

The length of handles may be adjusted because the excess will be covered by the pocket.

Begin stitching handle 1" from top of **E**, stitch along both sides of handle to secure.


Stitch a handle to both tote front and back.




make 2

5. Fold pocket back (should cover bottom of handles).

Topstitch both edges of handle (that are under pocket) to create pocket dividers. Stitch to the bottom of the pockets on both pieces.




6. Pin handles away from the top raw edge, then place lining **C** 15 1/2" x 18 1/2" over both front and back pieces, right sides together. Match raw edges and secure with pin. Stitch TOP seam only. Press.



make 2

7. Place both front and back pieces, right sides together.

Match raw edges and secure with pins. Stitch 1/4" around edge, leave approximately 7" opening for turning along one side of the lining, at least 3" from corner.



8. Make boxed corners along the bottom by folding bottom seam to match the side seam, create a flattened triangle.

Stitch a line even with the bottom of the pocket seam. Repeat for all 4 corners (bag and lining). Pull bag thru opening.

Stitch opening closed and fold lining inside bag. Enjoy!!

