

## VICTORIAN ROMANCE – V1 OR V2 CORRECTION

### CORRECTION APPLIES TO STEP 11 - LOG CABIN BLOCK K – LAP, QUEEN AND KING SIZES

When I re-wrote the directions for this pattern, I decided to allow an extra  $\frac{1}{4}$ " on the final round of the log cabin, which gave the ability to trim the block to  $7\frac{1}{4}$ " x  $7\frac{1}{4}$ " in the final step to create a block the perfect size. When I added the extra  $\frac{1}{4}$ " to the width of the strip, I forgot to add it to the length of the final 3 strips – K11, K12 and K13.

**Choose** which correction to follow based on whether you have already cut your fabric or if you have not cut your fabric.

**Correction if Fabric is Already Cut and Ready to Sew:** Your first clue that something is off will happen when you attempt to sew K11 to the block and it doesn't fit. No stress – the following steps will walk you through trimming after adding each strip rather than trimming at the end of Step 11.

- **Step 1:** Measure the block after sewing K10 to the Log Cabin Block. Block should measure  $5\frac{1}{2}$ " wide (the width of the K10 strip just sewn to the quilt) by  $6\frac{5}{8}$ " long. Trim the length to  $6\frac{3}{8}$ ", trimming any excess off the K10 strip just sewn to block. This will bring the block into alignment to sew K11 to the block.
- **Step 2:** Sew K11 to block. Block should measure  $6\frac{3}{8}$ " wide (the width of the K11 strip just sewn to the quilt) by  $6\frac{5}{8}$ " long. Trim the length to  $6\frac{3}{8}$ ", trimming any excess off the K11 strip just sewn to block. This will bring the block into alignment to sew K12 to the block.
- **Step 3:** Sew K12 to block. Block should measure  $6\frac{3}{8}$ " wide (the width of the K12 strip just sewn to the quilt) by  $7\frac{1}{2}$ " long. Trim the length to  $7\frac{1}{4}$ ", trimming any excess off the K12 strip just sewn to block. This will bring the block into alignment to sew K13 to the block.
- **Step 4:** Sew K13 to block. Block should measure  $7\frac{1}{4}$ " wide (the width of the K13 strip just sewn to the quilt) by  $7\frac{1}{2}$ " long. Trim the length to  $7\frac{1}{4}$ ", trimming any excess off the K13 strip just sewn to block. These steps should create a perfect  $7\frac{1}{4}$ " x  $7\frac{1}{4}$ " Log Cabin block.

**Correction if Fabric Has Not Been Cut:**

Follow the cutting instructions below for K11, K12 and K13 strips and sew according to original instructions in pattern.

Lap, Queen and King Sizes			
Fabric	Yard(s)	Strips	Fabric Sub-Cuts
Pink Sprigs on Cream MAS8784-E		1 – $6\frac{5}{8}$ " x WOF	• Cut 16 – $6\frac{5}{8}$ " x $1\frac{5}{8}$ " Strip K11
Rosebud on Medium Green MAS8786-G		1 – $7\frac{3}{4}$ " x WOF 1 – $6\frac{5}{8}$ " x WOF	• Cut 16 – $7\frac{3}{4}$ " x $1\frac{5}{8}$ " Strip K13 • Cut 16 – $6\frac{5}{8}$ " x $1\frac{5}{8}$ " Strip K12