

# Stained Glass Love Letters

### **Supply List**

Book or Pattern: pattern supplied by Brenda

Sewing Machine #2 Pencil - or Sharpie Ultrafine Marker

#70/10 sewing machine needles Sewing Awl

Pins

Small Sharp Scissors - very helpful when cutting bias tape!!
Paper Scissors Fabric Scissors

Rotary Cutting Equipment Safety Pins - or Sulky KK2000 basting spray

Freezer Paper 12" x 10" Roxanne's Glue Baste It

Cotton Batting 14" x 16"

Woven Fusible Interfacing 11" x 9" - provided by Brenda

#### Fabric Prewashed and Pressed - DO NOT USE SPRAY STARCH


Please prewash all fabrics before class. Fusible products may not adhere to

unwashed fabric!!

4 ½" x 6 ½" Leaves Center Yellow 2" square 4" x 6" Petals Background 6" x 13" 6" x 8" Heart Border ½ yard Binding (black) ½ yard Backing (black) fat quarter Fusible bias tape 3 yards




If you have any questions before class, please feel free to email: brenda@bearpawproductions.com



## Stained Glass Love Letters

## Stained Glass Quilt Instructions

- 1 Center and trace the design on the adhesive (rough) side of the fusible interfacing using a ultra-fine point Sharpie pen.
- 2 Center and trace the design on the paper side of the freezer paper.
- 3 Cut the freezer paper pattern into templates. \* Cut directly on the drawn lines. If you are using a fabric with a directional print, you may choose to draw arrows to indicate the direction of the print. \* Pieces that are of the same fabric, and side by side may be cut as one piece of fabric... Such as the leaves.



- 4 Place the cut freezer paper pieces on the right side of the chosen design fabric shiny side down. Press the freezer paper templates in place with a warm iron.
- 5 Cut the fabric pieces out 1/16" away from the edge of the paper template.
- 6 Position the fabric pieces on to the fusible side of the interfacing and press the fabrics in place. Use an applique press sheet to protect the sole of the iron from any exposed adhesive. Fabric pieces should over lap slightly.
- 7 Press the fusible bias tape in place. If any areas do not remain adhered, use a little dab of Roxanne's Glue Baste It to hold the layers in place. Be sure to follow the sequence of bias tape placement on the pattern.
- 8 Trim the design to 8" x 10".
- 9 Cut strips of border fabric as follows:

2 strips 2 1/2" x 8"

2 strips 2 1/2" x 14"

- 10 Apply the borders to the design block using a 1/4" seam allowance. Press the seams toward the border strips.
- 11 Layer the quilt top with batting and backing. Stitch the bias tape in place along both edges. Stipple quilt the border if desired. Trim the excess batting and backing to the edge of the design.
- 12 Bind the quilt to finish