



Finished Size: 52" x 59" (1.32m x 1.50m)

Finished Block Size: N/A

Fabric Collection Name and Fabric Designer: Holly Woods by Cathy Walters

Technique: Pieced

Designed by: Denise Russell of Pieced Brain

Skill Level: Beginner

Teamwork Wall Hanging



FABRIC REQUIREMENTS

			Yards	Meters
A	Woodland Toss - Slate	9234-79	3/8	0.34
B	Evening Snow - Slate	9236-79*	5/8	0.57
C	Shaded Dots - Coral	9238-83	3/8	0.34
D	Vintage Ornaments - Slate	9240-79	3/4	0.69
E	Hanging Lights - Ice	9243-17	5/8	0.57
F	Bottlebrush Tree Toss - Coral	9246-83	3/8	0.34
G	Woodland Decorating Panel – Slate	9247P-79	1	0.91
44"	Knitting Raccoon - Pearl	9242-11	3 1/3	3.05
108"			1 2/3	1.52

*Binding

**Backing

Additional Requirements

100% Cotton Thread

Batting: 60" x 67" (1.52m x 1.70m)

CUTTING

Notes:

- Please make sure to check studioefabrics.net for pattern updates prior to starting the project.
- All strips are cut across the width of fabric (WOF) from selvage to selvage edge unless otherwise noted.

Fabric A, cut:

(6) 1½" x WOF for border 6

Fabric E, cut:

(10) 1½" x WOF: 5 each for borders 1 and 4

Fabric B, cut:

(6) 2½" x WOF for binding

Fabric F, cut:

(5) 2" x WOF for border 2

Fabric C, cut:

(5) 1½" x WOF for border 3

Fabric G:

Trim panel to 35½" x 42½"

Fabric D, cut:

(6) 3½" x WOF for border 5

QUILT TOP ASSEMBLY

Notes: Follow the Quilt Layout Diagram (page X) while assembling the quilt top. All seam allowances are $\frac{1}{4}$ " (0.64cm). Sew pieces with right sides together. Press seam allowances open unless otherwise indicated.

For border 1, measure the length of the quilt top through the center. If, after trimming the selvages from the strips, there isn't enough usable fabric, sew (3) $1\frac{1}{2}$ " **Fabric E** strips together end to end using diagonal seams. Trim the long strip into (2) $42\frac{1}{2}$ " strips. Otherwise, trim (2) $1\frac{1}{2}$ " **Fabric E** strips to the measured length. Sew one strip to each side of the **Fabric G** panel and press the seams toward the borders. Measure the width of the quilt top through the center. Trim the 2 remaining border strips to that length and sew one to the top and the other to the bottom. Press the seams toward the borders.

For border 2, sew (3) 2" **Fabric F** strips together end to end using diagonal seams. Measure the length of the quilt top through the center and cut 2 border strips to that length. Sew the strips to either side of the quilt top and press the seams toward the borders. Measure the width of the quilt top through the center. Trim 2 border strips to that length and sew one to the top and one to the bottom. Press the seams toward the borders.

Repeat step 2 with the (5) $1\frac{1}{2}$ " **Fabric C** strips to make and add border 3.

For border 4, sew the (5) $1\frac{1}{2}$ " **Fabric E** strips together end to end using diagonal seams. Measure the vertical length of the quilt top through the center and cut two border strips to that length. Sew one strip to each side of the quilt top and press the seams toward the borders. Measure the width of the quilt top through the center. Cut two border strips to that length and sew one to the top and one to the bottom. Press the seams toward the borders.

Repeat step 4 with the (6) $3\frac{1}{2}$ " **Fabric D** strips to make and add border 5.

Repeat step 4 with the (6) $1\frac{1}{2}$ " **Fabric A** strips to make and add border 6.

FINISHING

Sew together the (6) 2½" **Fabric B** binding strips end to end using diagonal seams. Press the seams open. Press the binding strip in half with the wrong sides together.

Layer the backing (wrong side up), batting, and quilt top (right side up). Baste the layers together and quilt as desired. Trim excess batting and backing even with the top of the quilt.

Leaving an 8" tail of binding and beginning along an edge of the quilt top, matching the raw edges of the binding to the raw edges of the quilt. Sew the binding to the outside edge around all four sides and miter corners. Stop sewing approximately 12" from where you started and backstitch.

Lay both loose ends of the binding flat along the quilt edge. Where these two loose ends meet, fold them back onto themselves and press to form a crease. Using this crease as your stitching line, sew the two open ends of the binding together, with the right sides matching. Trim the seam to ¼" and press it open. Finish sewing the binding to the quilt.

Turn the binding over the raw edge to the back of the quilt and hand or machine stitch in place.

