

GO! Modern Stockings

Finished Size: 10" x 15"



Dies Needed:

- GO! Santa Stocking (55854)
- GO! Strip Cutter-2" (1-1/2" Finished) (55025)
- GO! Parallelogram 45°-2-1/4" x 2-13/16" Sides (1-1/2" x 2-1/8" Finished) (55402)
- GO! Hexagon-1", 1-1/2", 2-1/2" Sides (3/4", 1-1/4", 2-1/4" Finished) (55011)

Fabric Requirements:

Fabric Color	Total Yardage
White	1-1/3 yards
Pink	1/2 yard
Aqua	1/2 yard
Chartreuse	1/2 yard
Dark Teal	1/2 yard
Batting	46" x 46"
Backing	1/2 yard
Lining	1 yard

Cutting Directions:


Fabric Color	Die	Number of Shapes to Cut
White	GO! Santa Stocking (55854)	Cut 2—9" x width of fabric (WOF) strips. Fanfold into 5-1/2" widths. Sub cut into 12—stocking cuffs (cuff only, not the foot of the stocking).
White	GO! Strip Cutter-2" (1-1/2" Finished) (55025)	Cut 3—2" x WOF strips. Sub cut into 6—2" x 20" strips.
Pink, Aqua, Chartreuse, and Dark Teal	GO! Strip Cutter-2" (1-1/2" finished) (55025)	From each color, cut 1—2" x WOF strips. Sub cut into 2—2" x 20" strips.
Pink, Aqua, Chartreuse, Dark Teal, and White	GO! Parallelogram 45°-2-1/4" x 2-13/16" Sides (55402)	From each color, cut 1—5" x WOF strips. Sub cut into 24—2-1/4" x 2" finished Parallelograms. If using a printed fabric, always cut fabric with printed side up to ensure parallelograms are all facing the same direction.
Pink, Aqua, Chartreuse, Dark Teal, and White	GO! Hexagon-1", 1-1/2", 2-1/2" Sides (55011)	From each color, cut 2—4" x WOF strips. Fanfold into 4" widths. Sub cut into 20—3" finished hexagons.
Aqua	GO! Santa Stocking (55854)	Cut 3—12" x width of fabric (WOF) strips. Sub cut into 6—stockings (foot only, not the cuff).
Lining	GO! Strip Cutter-2" (1-1/2" Finished) (55025)	Cut 1—2" x WOF strip. Sub cut into 1—2" x 20" strip.

Sewing Directions:

Press all seams open and use 1/4" seams, unless otherwise indicated.



Assemble Striped Stocking Panel

1. Sew six white, two pink, two aqua, one chartreuse, and one dark teal 2" strips together as shown in figure. Striped panel should measure approximately 20" x 18-1/2".
2. Cut a piece of batting to fit the panel and baste to the wrong side of the striped panel. Quilt as desired.
3. Place the batting side down on the GO! Santa Stocking die and cut one stocking shape (foot only, not cuff) from quilted striped panel.





Assemble Diamond Stocking Panel

1. Sew the parallelogram shapes into twelve columns of ten parallelograms each.
2. Sew the columns into pairs as shown.
3. Sew the six pairs into a diamond panel.
4. Cut a piece of batting to fit the panel and baste to the wrong side of the diamond panel. Quilt as desired.
5. Place the batting side down on the GO! Santa Stocking die and cut one stocking shape (foot only, not cuff) from the quilted diamond panel.




Assemble Hexagon Stocking Panel

1. On the wrong side of the cut hexagon shapes, mark 1/4" in from two of the corners (shown as dots in figure).
2. Place two hexagons right sides together. Sew a 1/4" seam from dot to dot. Repeat with additional hexagons to make a column of nine hexagons. Make a total of eight columns of hexagons.
3. Sew two rows of hexagons together by placing the first hexagons right sides together and similarly sewing from one 1/4" dot to the next 1/4" dot. Repeat with remaining seams down the column.




4. Repeat process to yield a hexagon panel of eight columns.



5. Cut a piece of batting to fit the panel and baste to wrong side of hexagon panel.
6. Place the batting side down on the GO! Santa Stocking die and cut one stocking shape (foot only, not cuff) from the quilted hexagon panel.


Assemble Stocking Backing

1. From the backing fabric, cut three pieces each 12" x 18". From the batting, cut three pieces each 12" x 18". Pair up each backing with a batting and smooth out the layers so they are straight and flat.
2. Place each of the backing/batting pairs backing sides down (batting side up) on the GO! Santa Stocking die one at a time and cut out a stocking shape (foot only, not cuff).
3. Place one of the batting/backing pairs right sides together on top of the striped stocking panel, lining up all of the raw edges. Start at the top corner and sew the layers together down the foot of the stocking using a 1/4" seam allowance. Leave the entire top edge open. Repeat with diamond and hexagon panels.




Assemble Stocking Lining

1. Place two cut lining pieces right sides together and sew down the foot of the stocking using a 1/4" seam allowance. Leave the top of the stocking open and leave the stocking as is (do not turn right sides out). Repeat with remaining lining pieces to yield three linings.
2. Slide each of the linings into one of the outer stocking units so the raw edges at the top are lined up. Sew a 1/8" seam around the raw edges to securely attach the lining to the outer stocking.




Assemble the Hang Tab

1. Fold the aqua 2" x 20" strip in half the long way, press, then unfold to create a crease.
2. Fold the top edge down to the center crease, press into place.
3. Fold the bottom edge up to the center crease, press into place.
4. Fold the strip in half along the original center crease line and press again. Top stitch along the open edge.
5. Cut the strip into three 6" lengths.




Assemble the Cuff


1. Sew four cut white cuff pieces together. Press all seams open. Keep the wrong-side of the cuff facing up.




2. Cut a piece of batting 14-1/4" x 4-1/4". Place the batting on the bottom half of the wrong side of the cuff. Fold the right side of the batting/cuff combo around the back (right sides together) and align with the left side of the cuff. Sew the cuff and batting layers together down the left side of the unit using a 1/4" seam.



3. Roll the top edge of the cuff down around the batting to create a tube with the batting fully enclosed by the cuff.



4. Fold an aqua Hang Tab in half so it is 3" long. Place the raw edge of hang tag on the left seam of the cuff, aligning the raw edges. Sew the tag onto the cuff with a 1/8" seam.



5. Repeat steps 1-4 to create three cuffs.

Assemble the Stocking

1. Flip the cuff so the raw edges are facing up and slide into one of the prepared stockings so the raw edges of the cuff line up exactly with the raw edges of the stocking/lining. Check to make sure that the hang tag is hanging down into the stocking and didn't get folded up.
2. Sew around the entire perimeter of the stocking opening with a 1/4" seam. Make sure to catch the raw edges of all of the layers in the seam.
3. Flip the cuff up and out of the stocking opening and turn down to conceal the seam just sewn. The cuff can be turned down as much or as little as wanted to achieve the desired look.

