

HoopSisters

SEE WHAT YOUR EMBROIDERY
MACHINE CAN REALLY DO

Christmas Nutcracker Instructions

Finished Size: 14" x 26½"

Requires a minimum sewing field of 6½" x 7"

The Christmas Nutcracker is a classic design with ornate details adorning the nutcracker's jacket, crown and more. Using both the stitch-and-flip and applique techniques, this nutcracker is fun to stitch and the perfect décor for your home at Christmastime.




HoopSisters


SEE WHAT YOUR EMBROIDERY
MACHINE CAN REALLY DO

Christmas Nutcracker File Preview—Blocks


File Name: CornerA
File Size: 3.50" x 3.50"




File Name: BdrTop
File Size: 6.90" x 3.50"




File Name: CornerB
File Size: 3.50" x 3.50"




File Name: BdrSide
File Size: 3.50" x 6.50"




File Name: TopBlock
File Size: 6.90" x 6.50"




File Name: BdrSide
File Size: 3.50" x 6.50"




File Name: BdrSide
File Size: 3.50" x 6.50"




File Name: MidBlock
File Size: 6.90" x 6.50"




File Name: BdrSide
File Size: 3.50" x 6.50"




File Name: BdrSide
File Size: 3.50" x 6.50"




File Name: BtmBlock
File Size: 6.90" x 6.50"




File Name: BdrSide
File Size: 3.50" x 6.50"




File Name: CornerB
File Size: 3.50" x 3.50"



File Name: BdrBtm
File Size: 6.90" x 3.50"




File Name: CornerA
File Size: 3.50" x 3.50"



HoopSisters

SEE WHAT YOUR EMBROIDERY
MACHINE CAN REALLY DO

Christmas Nutcracker Fabric Map





Christmas Nutcracker Supply List

Finished Size: 14" x 26½"

Minimum Hoop Size: 6½" x 6⅝"

Battilizer® 5 yard package	Optional Wool Batting Craft Size Package	
15 pieces large enough to fit hoop	3—6½" x 6⅞"	2—3½" x 6⅞"
	6—3½" x 6½"	4—3½" x 3½"

Background Fabric	Pants & Border Fabric	Jacket Fabric	Boots Fabric	Cuff & Crown Fabric	Hands & Face Fabric	Hair Fabric
Fat Quarter	1/2 yard	Fat Quarter	Fat Quarter or Scraps	Fat Quarter	Fat Quarter or Scraps	Fat Quarter or Scraps
2—1½" x 2½" 2—3" x 5¼" 2—1½" x 3½" 2—2¾" x 4½" 1—1½" x 4" 2—3" x 7½" 1—1½" x 7½" 2—1½" x 6"	2—2¾" x 4" 2—2¼" x 2¾" 2—4½" x 8" 6—4½" x 7½" 4—4½" x 4½"	1—3½" x 5¼" 4—2½" x 3¾" 1—3½" x 4¾" 1—4½" x 5½" 1—3" x 5"	2—2½" x 5¼" 1—2" x 4½"	1—3¼" x 4½" 2—2" x 2½" 1—1¾" x 5¾" 1—1½" x 4¼" 1—2" x 4½" 1—2½" x 5" 1—1½" x 1½"	1—3" x 4½" 2—2" x 2"	1—2¾" x 3" 2—2" x 3¼" 1—1½" x 3"


Binding Fabric 1/4 yard
3—2½" strips x width of fabric
Backing Fabric 1/2 yard
1—16" x 29"

Additional Supplies to have on hand:	
• Trimmer by George 3.0	• HoopScissors Mini
Threads to have on hand:	
<i>Polyester Embroidery Threads Recommended</i>	
• Thread to match each Fabric	• Embroidery Bobbin Thread
• Thread for quilting on border blocks	• Vanish Lite Water Soluble Thread
• Thread for face details	• Mono.Poly Invisible Thread







HoopSisters


SEE WHAT YOUR EMBROIDERY
MACHINE CAN REALLY DO

TopBlock
Stitch 1









Top Block

<p>1)</p>  <p>Hoop <u>Battilizer</u>®. Place <u>water soluble thread</u> in the needle and <u>embroidery bobbin thread</u> in the bobbin and sew the placement stitch onto Battilizer®.</p>	<p>2)</p>  <p>This step is optional. Skip to Step 3 if additional wool batting not being used.</p> <p>Raise height of presser foot to skim over wool to avoid it getting caught. Press edges of <u>wool batting</u> to flatten. Place wool batting inside placement stitch. Using <u>water soluble thread</u> in the needle, sew the zigzag stitch.</p>	<p>3)</p>  <p>Continuing with the <u>same thread</u>, sew placement stitch.</p>
<p>4)</p>  <p>Align <u>Jacket Fabric (3½" x 5¼")</u> over placement. Sew tack down and beard placement using <u>water soluble thread</u>.</p> <p>Use HoopScissors to trim scant 1/4" on inside of block (red).</p>	<p>5)</p>  <p>Place <u>Background Fabric (1½" x 2½")</u> right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>6)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>.</p> <p>Use HoopScissors to trim scant 1/4" from tack down stitching.</p>









Top Block Continued

<p>7)</p>  <p>Place <u>Background Fabric</u> ($1\frac{1}{2}'' \times 2\frac{1}{2}''$) right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>8)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>. Use HoopScissors to trim scant $\frac{1}{4}''$ from tack down stitching.</p>	<p>9)</p>  <p>Place <u>Jacket Fabric</u> ($2\frac{1}{2}'' \times 3\frac{1}{4}''$), for right arm, right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>
<p>10)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>. Use HoopScissors to trim scant $\frac{1}{4}''$ from tack down stitching.</p>	<p>11)</p>  <p>Place <u>Jacket Fabric</u> ($2\frac{1}{2}'' \times 3\frac{1}{4}''$), for left arm, right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>12)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>. Use HoopScissors to trim scant $\frac{1}{4}''$ from tack down stitching.</p>




Top Block Continued

<p>13)</p>  <p>Place <u>Background Fabric (3" x 5¼")</u> right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>14)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>. Use HoopScissors to trim scant 1/4" from tack down stitching.</p>	<p>15)</p>  <p>Place <u>Background Fabric (3" x 5¼")</u> right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>
<p>16)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>. Use HoopScissors to trim scant 1/4" from tack down stitching.</p>	<p>17)</p>  <p>Sew tack down along edges of block using <u>water soluble thread</u>.</p>	<p>18)</p>  <p>Sew shoulder details using <u>thread that contrasts fabric</u>.</p>







HoopSisters


SEE WHAT YOUR EMBROIDERY
MACHINE CAN REALLY DO

TopBlock
Stitch 1










Top Block Continued

<p>19)</p>  <p>Sew details on jacket using <u>thread color of your choice</u>.</p>	<p>20)</p>  <p>Align <u>Hair Fabric (2¾" x 3")</u> over placement. Sew tack down using <u>thread that matches fabric</u>.</p> <p>Use HoopScissors to trim scant 1/4" from tack down at top of beard (red). Use HoopScissors Mini to trim close to tack down stitching around remaining sides.</p>	<p>21)</p>  <p>Sew satin stitch using the <u>same thread</u>.</p>
<p>22)</p>  <p>Place <u>Face Fabric (3" x 4½")</u> right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>23)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down and placement using the <u>same thread</u>.</p> <p>Use HoopScissors Mini to trim close to tack down stitching along sides. Trim scant 1/4" from tack down along top side (red).</p>	<p>24)</p>  <p>Align <u>Hair Fabric (2—2" x 3¼")</u> over placement. Sew tack down using <u>thread that matches fabric</u>.</p> <p>Use HoopScissors Mini to trim close to tack down stitching around remaining sides.</p>









Top Block Continued

<p>25)</p>  <p>Sew satin stitch and details using <u>thread that matches fabric</u>.</p>	<p>26)</p>  <p>Align <u>Hair Fabric (1½" x 3")</u> over placement. Sew tack down using <u>thread that matches fabric</u>.</p> <p>Use HoopScissors Mini to trim close to tack down stitching around remaining sides.</p>	<p>27)</p>  <p>Sew satin stitch using <u>thread that matches fabric</u>.</p>
<p>28)</p>  <p>Stitch eyes using <u>white thread</u>.</p>	<p>29)</p>  <p>Stitch eye color using <u>thread color of your choice</u>.</p>	<p>30)</p>  <p>Stitch pupils using <u>black thread</u>.</p>




Top Block Continued

<p>31)</p>  <p>Stitch reflection in eyes using <u>white thread</u>.</p>	<p>32)</p>  <p>Stitch nutcracker eyebrows using <u>thread color of your choice</u>.</p>	<p>33)</p>  <p>Sew quilting using <u>thread that matches fabric</u>.</p>
<p>34)</p>  <p>Align <u>Cuff & Crown Fabric</u> (3¼" x 4½") over placement. Sew tack down using <u>water soluble thread</u>.</p> <p>Use HoopScissors Mini to trim close to tack down on inside edges of block (red).</p>	<p>35)</p>  <p>Stitch detail on crown using <u>thread color of choice</u>.</p>	<p>36)</p>  <p>Sew satin stitch using <u>thread that matches fabric</u>.</p>







HoopSisters

SEE WHAT YOUR EMBROIDERY
MACHINE CAN REALLY DO


MidBlock
Stitch 1









Middle Block


<p>1)</p>  <p>Hoop <u>Battilizer</u>®. Place <u>water soluble thread</u> in the needle and <u>embroidery bobbin thread</u> in the bobbin and sew the placement stitch onto Battilizer®.</p>	<p>2)</p>  <p>This step is optional. Skip to Step 3 if additional wool batting not being used.</p> <p>Raise height of presser foot to skim over wool to avoid it getting caught. Press edges of <u>wool batting</u> to flatten. Place wool batting inside placement stitch. Using <u>water soluble thread</u> in the needle, sew the zigzag stitch.</p>	<p>3)</p>  <p>Continuing with the <u>same thread</u>, sew placement stitch.</p>
<p>4)</p>  <p>Align <u>Jacket Fabric</u> (2½" x 3¼") over placement. Sew tack down using <u>water soluble thread</u>.</p>	<p>5)</p>  <p>Place <u>Background Fabric</u> (1½" x 3½") right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>6)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>.</p> <p>Use HoopScissors to trim scant ¼" from tack down stitching.</p>

MidBlock
Stitch 1










Middle Block Continued

<p>7)</p>  <p>Place <u>Jacket Fabric</u> ($3\frac{1}{2}'' \times 4\frac{3}{4}''$) right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>8)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>.</p> <p>Use HoopScissors to trim scant $\frac{1}{4}''$ from tack down stitching.</p>	<p>9)</p>  <p>Place <u>Background Fabric</u> ($1\frac{1}{2}'' \times 3\frac{1}{2}''$) right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>
<p>10)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>.</p> <p>Use HoopScissors to trim scant $\frac{1}{4}''$ from tack down stitching.</p>	<p>11)</p>  <p>Place <u>Jacket Fabric</u> ($2\frac{1}{2}'' \times 3\frac{1}{4}''$) right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>12)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>.</p> <p>Use HoopScissors to trim scant $\frac{1}{4}''$ from tack down stitching.</p>









Middle Block Continued


<p>13)</p>  <p>Align <u>Pants Fabric</u> ($2\frac{3}{4}$" x 4"), for right leg, over placement. Sew tack down using <u>water soluble thread</u>.</p>	<p>14)</p>  <p>Place <u>Background Fabric</u> ($2\frac{3}{4}$" x $4\frac{1}{2}$"") right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>15)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down and placement for applique using the <u>same thread</u>.</p> <p>Use HoopScissors to trim scant $\frac{1}{4}$" from tack down stitching.</p>
<p>16)</p>  <p>Place <u>Background Fabric</u> ($1\frac{1}{2}$" x 4") right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>17)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>.</p> <p>Use HoopScissors to trim scant $\frac{1}{4}$" from tack down stitching.</p>	<p>18)</p>  <p>Place <u>Pants Fabric</u> ($2\frac{3}{4}$" x 4"), for left leg, right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>









Middle Block Continued

<p>19)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>.</p> <p>Use HoopScissors to trim scant 1/4" from tack down stitching.</p>	<p>20)</p>  <p>Place <u>Background Fabric (2¾" x 4½")</u> right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>21)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down and placement for applique using the <u>same thread</u>.</p> <p>Use HoopScissors to trim scant 1/4" from tack down stitching.</p>
<p>22)</p>  <p>Align <u>Hands Fabric (2—2" x 2")</u> over placement. Sew tack down using <u>thread that matches fabric</u>.</p> <p>Use HoopScissors Mini to trim close to tack down on rounded edges. Trim scant 1/4" along straight lines at top (red).</p>	<p>23)</p>  <p>Sew satin stitch using <u>thread that matches fabric</u>.</p>	<p>24)</p>  <p>Sew placement stitches using <u>water soluble thread</u>. These placement lines will be used in Steps 27 & 28.</p>


MidBlock
Stitch 1



Middle Block Continued

<p>25)</p>  <p>Place <u>Cuff Fabric (2" x 2½")</u> right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>26)</p>  <p>Place <u>Cuff Fabric (2" x 2½")</u> right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>27)</p>  <p>Flip Fabric right side up, finger press and smooth out. Tuck Fabric under, wrong sides together working fabric to be even with placement line stitched in Step 24. Finger press and smooth fabric. Slow down machine and sew tack down using <u>thread that matches fabric</u>.</p>
<p>28)</p>  <p>Flip Fabric right side up, finger press and smooth out. Tuck Fabric under, wrong sides together working fabric to be even with placement line stitched in Step 24. Finger press and smooth fabric. Slow down machine and sew tack down using <u>thread that matches fabric</u>.</p>	<p>29)</p>  <p>Place <u>Jacket Fabric (4½" x 5½")</u> right side down, raw edges approximately even. Use a <u>thread that matches fabric</u> to sew seam.</p>	<p>30)</p>  <p>Do not flip fabric yet! Sew placement stitches using the <u>same thread</u>.</p>


MidBlock
Stitch 1









Middle Block Continued

<p>31)</p> <p>Flip Fabric right side up, finger press and smooth out. Tuck Fabric under, wrong sides together working fabric to be even with placement line stitched in Step 30. Finger press and smooth fabric. Slow down machine and sew tack down using <u>thread that matches fabric</u>.</p>	<p>32)</p> <p>Tack down fabric around edge of block using <u>water soluble thread</u>.</p>	<p>33)</p> <p>Sew quilting using <u>thread that matches fabric</u>.</p>
<p>34)</p> <p>Stitch details on pants using <u>thread color of choice</u>.</p>	<p>35)</p> <p>Stitch details using a <u>contrasting thread</u>.</p>	<p>36)</p> <p>Sew details on jacket using <u>thread color of your choice</u>.</p>

MidBlock
Stitch 1




Middle Block Continued

<p>37)</p>  <p>Sew jacket details using <u>thread color of your choice</u>.</p>	<p>38)</p>  <p>Align Cuff Fabric ($1\frac{3}{4}$" x $5\frac{3}{4}$") over placement. Using a <u>contrasting thread</u>, stitch tack down and details.</p> <p>Use HoopScissors Mini to trim close to tack down on all sides.</p>	<p>39)</p>  <p>Sew placement stitch using <u>water soluble thread</u>.</p>
<p>40)</p>  <p>Align Cuff Fabric ($1\frac{1}{2}$" x $4\frac{1}{4}$") over placement. Sew tack down using <u>thread that matches fabric</u>.</p>	<p>41)</p>  <p>Sew satin stitch using <u>thread that matches fabric</u>.</p>	<p>42)</p>  <p>Sew details on jacket using <u>thread color of your choice</u>.</p>







HoopSisters

SEE WHAT YOUR EMBROIDERY
MACHINE CAN REALLY DO

BtmBlock
Stitch 1




Bottom Block

<p>1)</p>  <p>Hoop <u>Battilizer</u>®. Place <u>water soluble thread</u> in the needle and <u>embroidery bobbin thread</u> in the bobbin and sew the placement stitch onto Battilizer®.</p>	<p>2)</p>  <p>This step is optional. Skip to Step 3 if additional wool batting not being used.</p> <p>Raise height of presser foot to skim over wool to avoid it getting caught. Press edges of <u>wool batting</u> to flatten. Place wool batting inside placement stitch. Using <u>water soluble thread</u> in the needle, sew the zigzag stitch.</p>	<p>3)</p>  <p>Continuing with the <u>same thread</u>, sew placement stitch.</p>
<p>4)</p>  <p>Align <u>Background Fabric</u> (3" x 7½") over placement. Sew tack down using <u>water soluble thread</u>.</p> <p>Use HoopScissors to trim scant 1/4" from tack down stitching on inside of block (red).</p>	<p>5)</p>  <p>Place <u>Pants Fabric</u> (2¼" x 2¾"), for right leg, right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>6)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>.</p> <p>Use HoopScissors to trim scant 1/4" from tack down stitching.</p>







HoopSisters

SEE WHAT YOUR EMBROIDERY
MACHINE CAN REALLY DO

BtmBlock
Stitch 1



Bottom Block


<p>7)</p>  <p>Place <u>Boots Fabric</u> (2½" x 5¼"), for right boot, right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>8)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>. Use HoopScissors to trim scant ¼" from tack down stitching.</p>	<p>9)</p>  <p>Place <u>Background Fabric</u> (1½" x 6") right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>
<p>10)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>. Use HoopScissors to trim scant ¼" from tack down stitching.</p>	<p>11)</p>  <p>Place <u>Background Fabric</u> (1½" x 7½") right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>12)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>. Use HoopScissors to trim scant ¼" from tack down stitching.</p>

HoopSisters







SEE WHAT YOUR EMBROIDERY
MACHINE CAN REALLY DO

BtmBlock


Stitch 1









Bottom Block

<p>13)</p>  <p>Place <u>Pants Fabric</u> (2¼" x 2¾"), for left leg, right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>14)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>. Use HoopScissors to trim scant 1/4" from tack down stitching.</p>	<p>15)</p>  <p>Place <u>Boots Fabric</u> (2½" x 5¼"), for left boot, right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>
<p>16)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>. Use HoopScissors to trim scant 1/4" from tack down stitching.</p>	<p>17)</p>  <p>Place <u>Background Fabric</u> (1½" x 6") right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>18)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>. Use HoopScissors to trim scant 1/4" from tack down stitching.</p>

BtmBlock
Stitch 1




Bottom Block

<p>19)</p>  <p>Place <u>Background Fabric (3" x 7½")</u> right side down, raw edges approximately even. Use a <u>neutral thread</u> to sew seam.</p>	<p>20)</p>  <p>Flip Fabric right side up, finger press and smooth out. Sew tack down using the <u>same thread</u>.</p>	<p>21)</p>  <p>Stitch quilting using <u>thread that matches fabric</u>.</p>
<p>22)</p>  <p>Stitch details on pants using <u>thread color of choice</u>.</p>	<p>23)</p>  <p>Align <u>Cuff Fabric (2" x 4½")</u> over placement. Using a <u>contrasting thread</u>, stitch tack down and details.</p> <p>Use HoopScissors Mini to trim close to tack down on all sides.</p>	<p>24)</p>  <p>Sew satin stitch using <u>thread that matches fabric</u>.</p>




BtmBlock
Stitch 1



Bottom Block


25)



Align Boot Fabric (2" x 4½") over placement. Sew tack down using thread that matches fabric.


Use HoopScissors Mini to trim close to tack down on inside of block.

26)



Sew satin stitch using the same thread.

27)




Stitch laces using thread color of choice.

HoopSisters







SEE WHAT YOUR EMBROIDERY
MACHINE CAN REALLY DO

Copyright © 2024 HoopSisters



BdrTop—Stitch 1


BdrTop Block

<p>1)</p>  <p>Hoop Battilizer®. Place <u>water soluble thread</u> in the needle and <u>embroidery bobbin thread</u> in the bobbin and sew the placement stitch onto Battilizer®.</p>	<p>2)</p>  <p>This step is optional. Skip to Step 3 if additional wool batting not being used.</p> <p>Raise height of presser foot to skim over wool to avoid it getting caught. Press edges of <u>wool batting</u> to flatten. Place wool batting inside placement stitch. Using <u>water soluble thread</u> in the needle, sew the zigzag stitch.</p>	<p>3)</p>  <p>Align <u>Border Fabric (4½" x 8")</u> over block. Sew tack down and placement using the <u>same thread</u>.</p>
<p>4)</p>  <p>Sew quilting using <u>thread color of your choice</u>.</p>	<p>5)</p>  <p>Align <u>Jacket Fabric (3" x 5")</u> over placement. Sew tack down and details using <u>thread that coordinates or matches fabric</u>.</p> <p>Use HoopScissors Mini to trim close to tack down stitching on all sides.</p>	<p>6)</p>  <p>Align <u>Crown Fabric (2½" x 5")</u> over placement. Sew tack down using <u>water soluble thread</u>.</p> <p>Use HoopScissors Mini to trim close to tack down stitching on inside edges of block.</p>

HoopSisters





SEE WHAT YOUR EMBROIDERY
MACHINE CAN REALLY DO

Copyright © 2024 HoopSisters



BdrTop—Stitch 1


BdrTop Block Continued

<p>7)</p>  <p>Sew satin stitch using <u>thread that matches fabric</u>.</p>	<p>8)</p>  <p>Sew satin stitch using <u>thread that matches fabric</u>.</p>	<p>9)</p>  <p>Align <u>Crown Fabric (1½" x 1½")</u> over placement. Sew tack down and placement using <u>thread that matches fabric</u>.</p> <p>Use HoopScissors Mini to trim close to tack down stitching on all sides.</p>
<p>10)</p>  <p>Sew satin stitch using the <u>same thread</u>.</p>		


HoopSisters

SEE WHAT YOUR EMBROIDERY MACHINE CAN REALLY DO

Copyright © 2024 HoopSisters







BdrSide—Stitch 6



BdrBtm—Stitch 1


BdrSide & BdrBtm Block

<p>1) BdrSide Shown</p>  <p>Hoop <u>Battilizer</u>®. Place <u>water soluble thread</u> in the needle and <u>embroidery bobbin thread</u> in the bobbin and sew the placement stitch onto Battilizer®.</p>	<p>2) BdrSide Shown</p>  <p>OPTIONAL</p> <p>This step is optional. Skip to Step 3 if additional wool batting not being used.</p> <p>Raise height of presser foot to skim over wool to avoid it getting caught. Press edges of <u>wool batting</u> to flatten. Place wool batting inside placement stitch. Using <u>water soluble thread</u> in the needle, sew the zigzag stitch.</p>	<p>3) BdrSide Shown</p>  <p>Align <u>Border Fabric</u> (Side—$4\frac{1}{2}$" x $7\frac{1}{2}$" / Btm—$4\frac{1}{2}$" x 8")) over block. Sew tack down and placement using the <u>same thread</u>.</p>
<p>4) BdrSide Shown</p>  <p>Sew quilting using <u>thread color of your choice</u>.</p>		

HoopSisters

SEE WHAT YOUR EMBROIDERY
MACHINE CAN REALLY DO

Copyright © 2024 HoopSisters









CornerA

CornerB

Corner Blocks

Stitch 2 Each

<p>1)</p>  <p>Hoop Battilizer®. Place <u>water soluble thread</u> in the needle and <u>embroidery bobbin thread</u> in the bobbin and sew the placement stitch onto Battilizer®.</p>	<p>2)</p>  <p>This step is optional. Skip to Step 3 if additional wool batting not being used.</p> <p>Raise height of presser foot to skim over wool to avoid it getting caught. Press edges of <u>wool batting</u> to flatten. Place wool batting inside placement stitch. Using <u>water soluble thread</u> in the needle, sew the zigzag stitch.</p>	<p>3)</p>  <p>Align <u>Border Fabric (4½" x 4½")</u> over block. Sew tack down using the <u>same thread</u>.</p>
<p>4)</p>  <p>Sew quilting using <u>thread color of your choice</u>.</p>	<p>Trimming Instructions</p> <p>Blue—Use Trimmer by George 3.0 to remove Battilizer up to basting stitch. Fabric on the front of the block will be trimmed 1/4" from basting stitches.</p> <p>Red—Trim 1/4" from basting stitches through all layers.</p> <p>Mark seam allowance with filename.</p> <div style="display: flex; justify-content: space-around;"> <div data-bbox="1175 1310 1406 1535">  <p>CornerA</p> </div> <div data-bbox="1175 1587 1406 1812">  <p>CornerB</p> </div> </div>	

HoopSisters


SEE WHAT YOUR EMBROIDERY
MACHINE CAN REALLY DO

Copyright © 2024 HoopSisters

Trimming

Blue—Use Trimmer by George 3.0 to remove Battilizer® up to basting stitch. Fabric on the front of the block will be trimmed 1/4” from basting stitches.

Red—Trim 1/4” from basting stitches through all layers.




Scan with any
QR reader to
learn how to
use the
Trimmer by
George 3.0!

HoopSisters

SEE WHAT YOUR EMBROIDERY
MACHINE CAN REALLY DO

Copyright © 2024 HoopSisters

Assembly



Block Assembly:

Sew blocks in Row 1 together, pressing seams to one side. Sew blocks in Row 2 together. Press seams in the opposite direction. Continue sewing blocks in Row 3, Row 4 and Row 5 together, alternating direction in which seams are pressed.

Sew Row 1 to Row 2; and, Row 3 to Row 4. Next, sew Rows 1 & 2 to Rows 3 & 4. Then, sew Row 4 to Row 5. Press seams to one side.

Layer and Quilting:

Place Backing Fabric (16" x 29") right side down on hard surface, taping edges to keep taut and hold in place. Place wall hanging right side up, centered over Backing Fabric.

Using a quilt basting spray or quilting safety pins, pin in place in several places, avoiding seams.

Place Clear MonoPoly Thread in the needle and bobbin. Beginning with seam between Rows 2 and 3, stitch in the ditch using a serpentine stitch. Continuing stitching in the ditch between Rows 3 and 4. Continue this quilting process until all the seams have been quilted. Using a longer basting stitch, baste the outside edge of quilt.

Trim Backing Fabric even with quilt. Use the three 2½" strips for binding, join strips using a diagonal seam. Add sleeve and bind wall hanging.