

## Embroidery Recipe Box



This is a project to make a Celtic Knots Bracelet. We will fuse Deco Magic to RNK Cork Fabric and then appliqué that onto to Floriani Wet N Gone.

Supplies needed are:

- Floriani Wet N Gone
- RNK Deco Magic (light is better than regular)
- Fabric of Choice ( RNK Cork Material)
- Embroidery Thread
- Metal Snaps


1)There are three sizes of this design to choose from. To choose your size first measure your wrist and add 3/4 inch to account for the overlap on the closure. Choose the bracelet that is closest in size.

Small - 7.1" / 180mm

Medium - 7.7" / 195mm

Large - 8.45" / 215mm

For smaller or larger sizes you can also use your Floriani software to adjust the smallest size smaller or the largest size larger.



## Blank Fabric Bracelet





## Embroidery Recipe Box



## Blank Fabric Bracelet




2) We need to Prep the material for the bracelet by fusing RNK Deco Magic Lite to the back of the Fabric or RNK Cork. The deco magic lite will add strength to the rock so the bracelet will be durable and strong and we use the lite product to also keep it flexible.

Note: You can swap a solid fabric color for the cork fabric.

3) Hoop Floriani Wet N Gone in a hoop large enough to fit the size of bracelet you need to sew. We are using RNK Perfect Grip tape to help the hoop hold the thin material. Place the grippy tape in-between the material and the inner hoop ring and hoop them together. Give the material a little tug to make it nice and taught.

4) Use the color of your border and sew the first color of the design that is the placement line where you will appliqué the cork fabric





## Embroidery Recipe Box



## Celtic Knots Bracelet



5) Place the stiffened material face up over the run stitch placement line.

6) Use the border color and sew the appliqué tack down stitch.

7) Use your appliqué scissors and trim the excess material away from around the run stitch tack down. Be sure to trim close (see photo) to be sure the border will cover it.

8) Continue to sew the colors of the design until complete.



### Complete Sewing Sequence

- 1) Bracelet appliqué placement line
- 2) Bracelet appliqué tack down line
- 3) Satin Border





## Embroidery Recipe Box



## Flower Bracelet / Cuff



- 9) Remove the hoop from the machine
- 10) Remove the Wet N Gone from the hoop.
- 11) Trim all knots and trail threads on the back side of the project to clean it up.



- 12) Trim the excess Wet N Gone from around the border of the bracelet. Be careful to trim close but not too close that you cut any of the stitches. See the photo below to show how little Wet N Gone to leave.
- 13) Remove the small bit of remaining Wet N Gone by wetting your finger and then touching the edge and get the material wet. Repeat this until all of the Wet N Gone is removed.





## Embroidery Recipe Box



## Flower Bracelet / Cuff



14) Use scissors to remove the Floriani Wet N Gone on the inside of the bracelet so the inside will be the deco magic.  
 15) We will use a metal snap kit to create the closure. Be sure to use a piece of wood and not hammer onto your cutting table.  
 16) Use one of the snaps to find the best place to make the holes. Hold the snap over the bracelet to find the place and use the snap to make a mark to show you where to make the holes. With the snaps I have its about 3/8 of an inch from the side and top.

17) Use the hole making tool and hammer two holes for the first side of the bracelet.

18) You can put the snaps on either end of the bracelet however you might like to plan how it feels best to snap it on. That also depends on what wrist you plan to wear it on. Trevor wears this on his right wrist and has chosen to add the male side of the snaps to the left side and the female snap on the right side, The female makes the front or top of the bracelet when the snaps are closed.

19) Follow the instructions from your snap tool set with two hammer the snap parts into the holes and complete the closure. Now you can try c enjoy.

