

Frosty Hollow[®] Quilt By MELINDA HIPSHER



Finished Size: 47 in x 54 ½ in (119.38 cm x 138.43 cm)

Fabric Needed

3 Wishes[®] Frosty Hollow Collection

- 1 Panel – Frosty Hollow 36 in Panel (24602-PNL-CTN-D)
- 1 ¼ yds – Frosty Snowman Toss (24599-BLK-CTN-D) for Piecing and Binding
- ¾ yd – Snowy Hollow Scenic (24601-WHT-CTN-D)
- ½ yd – Merry Motorcade (24600-BLU-CTN-D)
- 4 yds – Winter Hollow Patch (24598-MLT-CTN-D) for Backing

Additional Supplies Needed:

- 55 in x 63 in (139.7 cm x 160.02 cm) Cotton batting
- Piecing and sewing thread
- Quilting and sewing supplies
- Even-feed foot (optional for quilting)

Before You Begin

Read all instructions before beginning project. Do not pre-wash fabrics. Press fabrics with a dry iron on cotton setting before cutting. Use a ¼ in (6.35 mm) seam allowance and sew fabrics with right sides together (RST) unless otherwise noted. Press seams in the direction of the arrows. wof = width of fabric


Note: A printed panel may become slightly skewed during the finishing process. Check if panel is square before cutting by folding the panel so selvages meet. If all edges do not meet, pull firmly from corner to corner until the edges meet. Continue until all corners are square.

Cutting


Use a rotary cutter and ruler to cut the size and number of squares and rectangles from each fabric listed below.



Frosty Hollow 36 in Panel (24602-PNL-CTN-D)
1 yd x wof (91.44 cm x 106.68 cm)
 Fussy Cut 9 – 10 ¼ in x 12 ¾ in (26.04 cm x 32.39 cm)



Snowy Hollow Scenic (24601-WHT-CTN-D) – ¾ yd (68.58 cm x 106.68 cm)
 Cut 2 – 41 ½ in x 3 ½ in (104.14 cm x 8.89 cm)
 Cut 4 – 24 ½ in x 3 ½ in (62.23 cm x 8.89 cm)




Frosty Snowman Toss (24599-BLK-CTN-D) – 1 ¼ yds (111.76 cm x 106.68 cm)
 Cut 5 – 2 ½ in x wof (6.35 cm x 106.68 cm) for Binding
 Cut 12 – 12 ½ in x 3 ½ in (31.75 cm x 8.89 cm)
 Cut 12 – 10 ½ in x 3 ½ in (26.67 cm x 8.89 cm)
 Cut 4 – 3 ½ in x 3 ½ in (8.89 cm x 8.89 cm)



Merry Motorcade (24600-BLU-CTN-D) – ½ yd (30.48 cm x 106.68 cm)
 Cut 12 – 3 ½ in x 3 ½ in (8.89 cm x 8.89 cm)

Sewing


1. Place four Merry Motorcade squares $3\frac{1}{2}$ in x $3\frac{1}{2}$ in (8.89 cm x 8.89 cm) and three Frosty Snowman Toss $10\frac{1}{2}$ in x $3\frac{1}{2}$ in (26.67 cm x 8.89 cm) as shown in Diagram A. Pin RST, sew and press to make one Horizontal Sashing strip $3\frac{1}{2}$ in x 41 in (8.89 cm x 104.14 cm). Make four.



2. Place a Frosty Snowman Toss square $3\frac{1}{2}$ in x $3\frac{1}{2}$ in (8.89 cm x 8.89 cm) on each side of a Snowy Hollow Scenic rectangle $41\frac{1}{2}$ in x $3\frac{1}{2}$ in (104.14 cm x 8.89 cm) as shown in Diagram B. Pin RST, sew and press to make the Top Border $3\frac{1}{2}$ in x 47 in (8.89 cm x 119.38 cm). Repeat to make the Bottom Border.



3. Place four Frosty Snowman Toss rectangles $12\frac{1}{2}$ in x $3\frac{1}{2}$ in (31.75 cm x 8.89 cm), three Fussy Cut Panel rectangles $10\frac{1}{4}$ in x $12\frac{3}{4}$ in (26.04 cm x 32.39 cm) as shown in Diagram C. Pin RST, sew and press to make Row 1 – 12 in x 41 in (31.75 cm x 104.14 cm).




4. Place four Frosty Snowman Toss rectangles $12\frac{1}{2}$ in x $3\frac{1}{2}$ in (31.75 cm x 8.89 cm), three Fussy Cut Panel rectangles $10\frac{1}{4}$ in x $12\frac{3}{4}$ in (26.04 cm x 32.39 cm) as shown in Diagram D. Pin RST, sew and press to make Row 2 – 12 in x 41 in (31.75 cm x 104.14 cm).




5. Place four Frosty Snowman Toss rectangles 12 ½ in x 3 ½ in (31.75 cm x 8.89 cm), three Fussy Cut Panel rectangles 10 ¼ in x 12 ¾ in (26.04 cm x 32.39 cm) as shown in Diagram E. Pin RST, sew and press to make Row 3 – 12 in x 41 in (31.75 cm x 104.14 cm).

Dia. E



6. Remove selvages from four Snowy Hollow Scenic strips 24 ½ in x 3 ½ in (62.23 cm x 8.89 cm) and sew end to end to make one long strip. From the sewn strip, cut two strips 3 ½ in x 48 ½ in (8.89 cm x 123.19 cm) to make Left and Right Borders as shown in Diagram F.

Dia. F



7. Place four Horizontal Sashing strips 3 ½ in x 41 in (8.89 cm x 104.14 cm) and Rows 1-3 – 12 in x 41 in (31.75 cm x 104.14 cm) as shown in Diagram G. Pin RST matching ends and seams, sew and press to make the Quilt Center 44 ½ in x 41 in (113.03 cm x 107.95 cm).



8. Place the Left and Right Borders 3 ½ in x 48 ½ in (8.89 cm x 123.19 cm) on each side of the Quilt Center 44 ½ in x 41 in (113.03 cm x 107.95 cm) as shown in Diagram H. Pin RST matching center and ends, sew and press. Place the Top and Bottom borders as shown; pin RST, matching ends and seams, sew and press to make the Quilt Top 47 in x 54 ½ in (119.38 cm x 138.43 cm).




Finishing

9. To make the Winter Hollow Patch Backing, remove the selvages and cut two pieces 42 in x 63 in (106.68 cm x 160.02 cm).
Note: Check orientation of the designs. Pin and sew the rectangles RST along the long edges as shown in Diagram I. Trim the Back to measure 55 in x 63 in (139.7 cm x 160.02 cm).



10. Press the finished Quilt Top and Backing fabric. Tape the Backing **wrong** side up on a firm surface. Layer Batting and Quilt Top (right side up). Baste the layers together with safety pins. Quilt as desired.
6. Once the quilting is complete, square up the corners and edges, trimming excess Backing and Batting even with the Quilt Top.
7. To make the Frosty Snowman Toss Binding, remove the selvages and sew the short ends of the five 2 ½ in x 42 in (6.35 cm x 106.68 cm) strips RST end to end at a 45 degree angle to make one continuous strip; press seams open. Press one short end ¼ in (6.35 mm) to the **wrong** side. Fold in half lengthwise with **wrong** sides together; press. Leaving a 2 in (5.08 cm) tail on the folded end, place cut edges of folded Binding even with the edge of the Quilt and sew, mitering the corners (Dia. J). Overlap ends, trim any excess and finish sewing the Binding. Fold the Binding over to the back and hand stitch.



Finished Care Instructions

Machine wash in cold water; gentle cycle. **Tip:** Before drying, check for fabric dyes that may have run. If fabric dyes run, rewash and rinse using Shout® Color Catcher®. Lay flat to dry or tumble dry low.