



Whimsy Winter Woodland Quilt



Featuring the Whimsy
Winter Woodland
Collection by
Deane Beesley

Shipping to stores June 2025!

Finished Size: 48 ½ in x 48 ½ in (123.19 cm x 123.19 cm)

Fabric Needed

3 Wishes Fabric® Whimsy Winter Woodland Collection

- 1 ½ yds – Winter Patchwork (23779-MLT-CTN-D)
- 1 ⅛ yds – Cozy Stockings (23777-BLK-CTN-D) includes Binding
- ⅝ yd – Woodland Friends (23776-MLT-CTN-D)
- ⅓ yd – Whimsy Woodland (23871-WHT-CTN-D)
- ⅓ yd – Winter Mittens (23780-GRN-CTN-D)
- ⅓ yd – Tossed Faces (23778-WHT-CTN-D)
- 2 ½ yds – Cozy Stockings (23777-BLK-CTN-D) Backing

Not included in the 3 Wishes Fabric® Whimsy Winter Woodland Collection

- ½ yd – Solid White Cotton

Additional Supplies Needed:

- 57 in x 57 in (144.78 cm x 144.78 cm) Cotton batting
- Piecing and sewing thread
- Quilting and sewing supplies
- Even-feed foot (optional for quilting)

Before You Begin

Read all instructions before beginning project. Do not pre-wash fabrics. Press fabrics with a dry iron on cotton setting before cutting. Use a ¼ in (6.35 mm) seam allowance and sew fabrics with right sides together (RST) unless otherwise noted. Press seams in the direction of the arrows. wof = width of fabric

Cutting

Use a rotary cutter and acrylic ruler to cut the number of squares and rectangles from each fabric listed below.



Winter Patchwork (23779-MLT-CTN-D) – 1 ½ yd (137.16 cm x 109.22 cm)

Cut 2 – 3 ½ in x 42 ½ in (8.89 cm x 107.95 cm)


Cut 2 – 3 ½ in x 48 ½ in (8.89 cm x 123.19 cm)

Cut 4 – 9 in x 9 in (22.86 cm x 22.86 cm)



Woodland Friends (23776-MLT-CTN-D) – ¾ yd (57.15 cm x 106.68 cm)

Fussy Cut 1 – 15 in x 16 ½ in (38.1 cm x 41.91 cm)




Whimsy Woodland (23871-WHT-CTN-D) – ½ yd (31.75 cm x 106.68 cm)

Cut 4 – 9 in x 9 in (22.86 cm x 22.86 cm)

Cut 2 – 19 ½ in x 2 in (49.53 cm x 5.08 cm)

Cut 2 – 16 ½ in x 2 ¾ in (41.91 cm x 7 cm)



Cozy Stockings (23777-BLK-CTN-D) – 1 ¼ yds (102.87 cm x 109.22 cm)

Cut 2 – 1 ½ in x 42 ½ in (3.81 cm x 107.95 cm)


Cut 2 – 1 ½ in x 40 ½ in (3.81 cm x 102.87 cm)

Cut 5 – 2 ½ in x wof (6.35 cm x 106.68 cm) for Binding

Cut 12 – 2 ½ in x 9 in (6.35 cm x 22.86 cm)

Cut 2 – 2 ½ in x 23 ½ in (6.35 cm x 59.69 cm)

Cut 2 – 2 ½ in x 19 ½ in (6.35 cm x 49.53 cm)



Solid White – ½ yd (45.72 cm x 106.68 cm)

Cut 48 – 3 in x 3 in (7.62 cm x 7.62 cm)



Winter Mittens (23780-GRN-CTN-D) – ½ yd (31.75 cm x 106.68 cm)

Cut 4 – 9 in x 9 in (22.86 cm x 22.86 cm)




Tossed Faces (23778-WHT-CTN-D) – ½ yd (31.75 cm x 106.68 cm)


Cut 4 – 9 in x 9 in (22.86 cm x 22.86 cm)

Sewing

1. Draw a diagonal line on the **wrong** side of a Solid White square 3 in x 3 in (7.62 cm x 7.62 cm). Place the square on one corner of a Winter Mittens square 9 in x 9 in (22.86 cm x 22.86 cm), sew on the drawn line and trim $\frac{1}{4}$ in (6.35 mm) from the sewn line; press. Repeat with the remaining three corners to make a Mittens Unit finishing at 9 in x 9 in (22.86 cm x 22.86 cm). Make four.



2. Repeat Step 1 with four Solid White Squares 3 in x 3 in (7.62 cm x 7.62 cm) for each Winter Patchwork, Tossed Faces, and Whimsy Woodland squares 9 in x 9 in (22.86 cm x 22.86 cm). Make 4 Patchwork Units, 2 Faces Units, and 2 Woodland Units.




3. Refer to Diagram C to add Borders to Center Unit.

Place a Whimsy Woodland strip $16\frac{1}{2}$ in x $2\frac{3}{4}$ in (41.91 cm x 7 cm) on each side of the Woodland Friends 15 in x $16\frac{1}{2}$ in (38.1 cm x 41.91 cm) center. Pin RST, sew and press. Place a Whimsy Woodland strip $19\frac{1}{2}$ in x 2 in (49.53 cm x 5.08 cm) on the top and bottom. Pin RST, sew and press.


Place a Cozy Stockings strip $2\frac{1}{2}$ in x $19\frac{1}{2}$ in (6.35 cm x 49.53 cm) on each side of the center with borders. Pin RST, sew and press. Place a Cozy Stockings strip $2\frac{1}{2}$ in x $23\frac{1}{2}$ in (6.35 cm x 59.69 cm) on the top and bottom. Pin RST, sew and press to make the Center Unit measuring $23\frac{1}{2}$ in x $23\frac{1}{2}$ in (59.69 cm x 59.69 cm).




4. Place three Cozy Stockings rectangles 2 ½ in x 9 in (6.35 cm x 22.86 cm), one Faces Unit 9 in x 9 in (22.86 cm x 22.86 cm), one Mittens Unit 9 in x 9 in (22.86 cm x 22.86 cm), one Patchwork Unit 9 in x 9 in (22.86 cm x 22.86 cm) and one Woodland Unit 9 in x 9 in (22.86 cm x 22.86 cm) as shown in Diagram D. Pin RST, sew and press to make the Top Inner Border finishing at 9 in x 40 ½ in (22.86 cm x 102.87 cm).




5. Place three Cozy Stockings rectangles 2 ½ in x 9 in (6.35 cm x 22.86 cm), one Woodland Unit 9 in x 9 in (22.86 cm x 22.86 cm), one Patchwork Unit 9 in x 9 in (22.86 cm x 22.86 cm), one Mittens Unit 9 in x 9 in (22.86 cm x 22.86 cm) and one Faces Unit 9 in x 9 in (22.86 cm x 22.86 cm) as shown in Diagram E. Pin RST, sew and press to make the Bottom Inner Border finishing at 9 in x 40 ½ in (22.86 cm x 102.87 cm).



6. Place three Cozy Stockings rectangles 2 ½ in x 9 in (6.35 cm x 22.86 cm), one Patchwork Unit 9 in x 9 in (22.86 cm x 22.86 cm) and one Mittens Unit 9 in x 9 in (22.86 cm x 22.86 cm) as shown in Diagram F. Pin RST, sew and press to make the Left Side Inner Border finishing at 9 in x 23 ½ in (22.86 cm x 59.69 cm).



7. Place three Cozy Stockings rectangles 2 ½ in x 9 in (6.35 cm x 22.86 cm), one Mittens Unit 9 in x 9 in (22.86 cm x 22.86 cm) and one Patchwork Unit 9 in x 9 in (22.86 cm x 22.86 cm) as shown in Diagram G. Pin RST, sew and press to make the Right Side Inner Border finishing at 9 in x 23 ½ in (22.86 cm x 59.69 cm).



8. Place the Left and Right Side Inner Borders 9 in x 23 ½ in (22.86 cm x 59.69 cm) on either side of the Center Unit 23 ½ in x 23 ½ in (59.69 cm x 59.69 cm) as shown in Diagram H. Pin RST, sew and press. Place the Top and Bottom Inner Borders, 9 in x 40 ½ in (22.86 cm x 102.87 cm) on the top and bottom respectively. Pin RST, sew and press to make the Quilt Center finishing at 40 ½ in x 40 ½ in (102.87 cm x 102.87 cm).




9. Refer to Diagram I to complete the Quilt Top.

Place a Cozy Stockings strip 1 ½ in x 40 ½ in (3.81 cm x 102.87 cm) on each side of the Quilt Center 40 ½ in x 40 ½ in (102.87 cm x 102.87 cm). Pin RST, sew and press. Place a Cozy Stockings strip 1 ½ in x 42 ½ in (3.81 cm x 107.95 cm) on the top and bottom. Pin RST, sew and press. The Quilt Center should measure 42 ½ in x 42 ½ in (107.95 cm x 107.95 cm).


Place a Winter Patchwork rectangle 3 ½ in x 42 ½ in (8.89 cm x 107.95 cm) on each side. Pin RST, sew and press. Place a Winter Patchwork 3 ½ in x 48 ½ in (8.89 cm x 123.19 cm) on the top and bottom. Pin RST, sew and press. The Quilt Top should measure 48 ½ in x 48 ½ in (123.19 cm x 123.19 cm).

Dia. I




Finishing

- Remove the selvages from the Cozy Stockings Backing fabric. Cut one piece 40 ¼ in x 57 in (102.87 cm x 144.78 cm) and two pieces 17 ¼ in x 28 ¾ in (43.82 cm x 73.03 cm). Pin the two smaller pieces RST on the short edges and sew; press. Pin the two sections RST and sew the long edges as shown in Diagram J. Press seams open or to one side. The Backing should measure 57 in x 57 in (144.78 cm x 144.78 cm).



- Press finished Quilt Top and Backing. Tape the Backing, **wrong** side up, to a firm surface. Layer Batting and Quilt Top (right side up). Baste the layers together with safety pins. Quilt as desired.
- Once quilting is complete, square up corners and edges, trimming excess Backing and Batting even with the Quilt Top.
- Follow Diagram L to make the Cozy Stockings Binding. Remove selvages and sew the short ends of the five 2 ½ in (6.35 cm) x wof strips RST end to end at a 45° angle to make one continuous strip; press seams open. Press one short end ¼ in (6.35 mm) to the **wrong** side. Fold in half lengthwise with **wrong** sides together; press. Leaving a 2 in (5.08 cm) tail on the folded end, place cut edges of folded Binding even with the edge of the Quilt Top and sew, mitering the corners. Overlap ends, trim any excess and finish sewing the Binding. Fold Binding over to back and hand stitch.



Finished Care Instructions

Machine wash in cold water; gentle cycle. Do not Bleach. **Tip:** Before drying, check for fabric dyes that may have run. If fabric dyes run, rewash and rinse using a color catcher to absorb loose dye. Lay flat to dry or tumble dry low.