

Adding Crystals to Embroidery:

Open a New File/Blank File

- Select *File* > *New*.
- In the Wizard, open the *Embroidery Normal* category and select *None*.
- Click *Next*.
- Place a radio dot in front of *From Embroidery*.
- Click on *Browse*.
- Navigate to *BERNINA DesignWorks Samples*.
- Select *CDW0016.ngs*. Open.
- In the *Hoop* selection drop-down, select *BERNINA Large Oval Hoop, 255 x 145, #48*.
- Click *Next*.
- Click *Finish*.



Editing the Design

- Select *Edit* > *Select All*.
- Increase the size of the design in *Tool Options*.
- Make sure *Proportional* is checked.
- Change the size of the *Height* to 180mm.

Adding a Single Crystal

- Select *Create Crystal Shape*.
- Choose these options in *Tool Options*:
 - ◊ Swarovski Round
 - ◊ Light Siam AB for Color
 - ◊ SS16/PP for Size
- Click on the Eiffel tower to set the crystal in the “crown” of the center section.




Adding a Row of Crystals

- Select *Create Bezier Shape*.
- Draw a line with two left clicks across the satin stitch while holding down the *Ctrl* key. The *Ctrl* key keeps the line straight.
- Right click to end the line.
- Press the space bar.
- In *Object Properties*, select *Crystals*.
- Choose these options in *Object Properties*:
 - ◊ Size 6 SS
 - ◊ Black Diamond for color
- Select *File* > *Save As* and name the file, *Adding Crystals to Embroidery*.



Notes:



Exporting the Design



- Select *Export*.
- Select your method for exporting the design.
- Using the *Export* icon only sends the embroidery file to the machine.
- Select *File> Export> Crystals to Machine*.
- In the dialog box that opens, click on the *Export* icon.
- This will send the crystal part of the design to the machine.

Notes: